

A Guide to Extend HIAB Size on Azure

Table of Contents

1	INTRODUCTION.....	4
2	SHUTDOWN HIAB VIRTUAL MACHINE.....	5
3	EXTEND HIAB DISK SPACE.....	7
4	START HIAB VIRTUAL MACHINE.....	8

About This Document

This document describes how to extend the disk of a running HIAB on Azure.

For support information, visit <https://www.outpost24.com/support>

Copyright

© 2018 Outpost24®. All rights reserved.

This document may only be redistributed unedited and unaltered. This document may be cited and referenced only if clearly crediting Outpost24® and this document as the source. Any other reproduction and redistribution in print or electronically is strictly prohibited without explicit permission.

Trademark

Outpost24®, OUTSCAN™, and HIAB™ are trademarks of Outpost24® in Sweden and other countries.

1 Introduction

Extending the disk size of HIAB on Azure can be achieved with the following steps:


- ▶ Shutdown HIAB Virtual Machine
- ▶ Extend the HIAB disk
- ▶ Start HIAB Virtual Machine

To update the disk size of your HIAB virtual machine, you need to access the Azure portal.


2 Shutdown HIAB Virtual Machine

Follow the below steps to shut down your virtual machine.

1. Open the HIAB virtual machine, and go to **Serial Console** menu.




2. Type **m** to view the **Maintenance** options.
3. Type **s** to shut down the virtual machine.



4. Type **yes** to confirm.

- Once the HIAB is shutdown, the virtual machine's status moves from **Running** to **Stopped** in your Virtual machines inventory.



Home > Virtual machines

Virtual machines Test

+ Add Reservations Edit columns Refresh Assign tags Start Restart Stop Delete Services


Subscriptions: Pay-As-You-Go - Don't see a subscription? Open Directory + Subscription settings

Filter by name: All resource groups All types All locations All tags No grouping

3 items

NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped	O24_RG	West US	-	Pay-As-You-Go

- Click on **Stop** to detach the resources and then be able to access the disk and change its size.



Home > Virtual machines

Virtual machines Test


+ Add Reservations Edit columns Refresh Assign tags Start Restart Stop Delete Services

Do you want to stop all the selected resources?

Yes No

NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped	O24_RG	West US	-	Pay-As-You-Go

The status of HIAB will be updated to **Stopped (deallocated)**.



Home > Virtual machines

Virtual machines Test

+ Add Reservations Edit columns Refresh Assign tags Start Restart Stop Delete Services

Subscriptions: Pay-As-You-Go - Don't see a subscription? Open Directory + Subscription settings

Filter by name: All resource groups All types All locations All tags No grouping

1 of 3 items selected


NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped (deallocated)	O24_RG	West US	-	Pay-As-You-Go

- You can now proceed with the following step and access the HIAB disk.


3 Extend HIAB Disk Space

To extend the disk of your HIAB virtual machine, open the HIAB virtual machine.

1. Go to the **Disks** menu.



2. Click on the **HIAB managed disk** to open a panel where you can extend the disk size as per your requirement.




3. Click **Save** to apply the changes.

4 Start HIAB Virtual Machine

Follow the below procedure to start the HIAB virtual machine.

1. Open **Virtual machines** menu.



Home > Virtual machines

Virtual machines

Test

+ Add Reservations Edit columns Refresh Assign tags Start Restart Stop Delete Services


Subscriptions: Pay-As-You-Go - Don't see a subscription? Open Directory + Subscription settings

Filter by name: All resource groups All types All locations All tags No grouping

1 of 3 items selected

NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped (deallocated)	O24_RG	West US	-	Pay-As-You-Go

2. Select the HIAB virtual machine and press the **Start** button.



Home > Virtual machines

Virtual machines

Test


+ Add Reservations Edit columns Refresh Assign tags Start Restart Stop Delete Services

Do you want to start all the selected resources?

Yes No

NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped (deallocated)	O24_RG	West US	-	Pay-As-You-Go

The status of the HIAB virtual machine is changed to **Running**.



Home > Virtual machines

Virtual machines

Test

+ Add Reservations Edit columns Refresh Assign tags Start Restart Stop Delete Services

Subscriptions: Pay-As-You-Go - Don't see a subscription? Open Directory + Subscription settings

Filter by name: All resource groups All types All locations All tags No grouping

3 items

NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Running	O24_RG	West US	-	Pay-As-You-Go

Note: The IP address can change if you are using a public IP address or an IP address set by DHCP. It is therefore recommended to set a static IP address.