

Extend HIAB Size on Azure

Table of Contents

1	INTRODUCTION.....	4
2	SHUTDOWN HIAB VIRTUAL MACHINE.....	5
3	EXTEND HIAB DISK SPACE.....	7
4	START HIAB VIRTUAL MACHINE.....	8

About This Document

This document describes how to extend the disk of a running HIAB on Azure.

For support information, visit <https://www.outpost24.com/support>

Copyright

© 2020 Outpost24®. All rights reserved.

This document may only be redistributed unedited and unaltered. This document may be cited and referenced only if clearly crediting Outpost24® and this document as the source. Any other reproduction and redistribution in print or electronically is strictly prohibited without explicit permission.

Trademark

Outpost24® and OUTSCAN™ are trademarks of Outpost24® in Sweden and other countries.

1 Introduction

Extending the disk size of HIAB on Azure can be achieved with the following steps:


- ▶ Shutdown HIAB Virtual Machine
- ▶ Extend the HIAB disk
- ▶ Start HIAB Virtual Machine

To update the disk size of your HIAB virtual machine, you need to access the Azure portal.


2 Shutdown HIAB Virtual Machine

Follow the below steps to shut down your virtual machine.

1. Open the HIAB virtual machine, and go to **Serial Console** menu.




2. Type **m** to view the **Maintenance** options.
3. Type **s** to shut down the virtual machine.




4. Type **yes** to confirm.

- Once the HIAB is shutdown, the virtual machine's status moves from **Running** to **Stopped** in your Virtual machines inventory.




NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped	O24_RG	West US	-	Pay-As-You-Go

- Click on **Stop** to detach the resources and then be able to access the disk and change its size.



NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped	O24_RG	West US	-	Pay-As-You-Go

The status of HIAB will be updated to **Stopped (deallocated)**.




NAME	TYPE	STATUS	RESOURCE GROUP	LOCATION	MAINTENANCE STAT...	SUBSCRIPTION
hiab	Virtual machine	Stopped (deallocated)	O24_RG	West US	-	Pay-As-You-Go

- You can now proceed with the following step and access the HIAB disk.


3 Extend HIAB Disk Space

To extend the disk of your HIAB virtual machine, open the HIAB virtual machine.

1. Go to the **Disks** menu.



2. Click on the **HIAB managed disk** to open a panel where you can extend the disk size as per your requirement.




3. Click **Save** to apply the changes.


4 Start HIAB Virtual Machine

Follow the below procedure to start the HIAB virtual machine.


1. Open **Virtual machines** menu.



2. Select the HIAB virtual machine and press the **Start** button.



The status of the HIAB virtual machine is changed to **Running**.



Note: The IP address can change if you are using a public IP address or an IP address set by DHCP. It is therefore recommended to set a static IP address.